


Unable to clear the Rx port Names Field in the Detailed Stream Result View especially with Port stray Frames enabled




Name/ID	Tx Port Name	Rx Port Names	Aggregated Rx Port Count	Port Stray Frames
StreamBloc...	Port //4/1	Port //4/1, Port //4/2	2	Yes
StreamBloc...	Port //4/2		0	N/A

Just right click and select Clear All Results Views or Clicking on the Clear Results Views Icon in the result view may not help

Please follow the steps to clear the Port names from the Field

On STC panel, Test Configuration -> Settings -> L2L3 ResultOptions -> select "Delete all analyzer streams when clearing results".



Right Click and Clear All Results View) or Click on Clear Result View Icon or use the command sequencer (Clear All Traffic Results),
The "Rx port names" value will be cleared